

# BluStar for PC Configuration Parameters

FEBRUARY 2015

RELEASE 3.2

REFERENCE GUIDE



## **NOTICE**

The information contained in this document is believed to be accurate in all respects but is not warranted by Mitel Networks™ Corporation (MITEL®). The information is subject to change without notice and should not be construed in any way as a commitment by Mitel or any of its affiliates or subsidiaries. Mitel and its affiliates and subsidiaries assume no responsibility for any errors or omissions in this document. Revisions of this document or new editions of it may be issued to incorporate such changes.

No part of this document can be reproduced or transmitted in any form or by any means - electronic or mechanical - for any purpose without written permission from Mitel Networks Corporation.

## **TRADEMARKS**

Mitel is a trademark of Mitel Networks Corporation.

Windows and Microsoft are trademarks of Microsoft Corporation.

Adobe Acrobat Reader is a registered trademark of Adobe Systems Incorporated.

Other product names mentioned in this document may be trademarks of their respective companies and are hereby acknowledged.

BluStar for PC Client Configuration Parameters  
Release 3.2 – February 2015

®, ™ Trademark of Mitel Networks Corporation  
© Copyright 2015 Mitel Networks Corporation  
All rights reserved

---

# CONTENTS

<b>1</b>	<b>Introduction .....</b>	<b>1</b>
1.1	Configuration files local storage location	1
1.2	System configuration file (aastra.cfg)	1
1.3	Model configuration file (BSCpc.cfg)	1
1.4	User read-only configuration file (BSCpc_<user>.cfg)	1
1.5	User configuration file (BSCpc_<user>_local.cfg)	1
1.6	User preferences file (BSCpc_prefs_<user>.cfg)	2
1.7	User local preferences file (BSCpc_MyPreferences_<user>.cfg)	2
1.8	Order of precedence	2
1.9	Parameter locking and parameter overriding	2
1.9.1	Parameter locking	2
1.9.2	Parameter overriding	3
<b>2</b>	<b>Log files .....</b>	<b>4</b>
2.1	Log files "BluStar_<yyymmtt>.log" and "MSRP_<yyymmtt>.log"	4
2.2	Log files "sipLog.txt" and "sipLog1.txt"	4
<b>3</b>	<b>Configuration Parameters .....</b>	<b>5</b>
3.1	Configuration Server Settings	5
3.1.1	config user name	5
3.1.2	config password	5
3.1.3	force config url credentials	5
3.1.4	configuration server uri	5
3.1.5	user config url	6
3.1.6	https validate certificates	6
3.1.7	user config upload	6
3.1.8	disable user preferences file transfer	7
3.1.9	force automatic configuration	7
3.2	Server, SIP and services connection settings	7
3.2.1	sip user name	7
3.2.2	sip password	7
3.2.3	sip proxy ip	8
3.2.4	sip proxy port	8
3.2.5	sip backup proxy ip	8
3.2.6	sip backup proxy port	8
3.2.7	sip outbound proxy	8
3.2.8	sip outbound proxy port	9
3.2.9	sip backup outbound proxy	9
3.2.10	sip backup outbound proxy port	9
3.2.11	sip presence server	9
3.2.12	sip presence port	9
3.2.13	sip presence outbound proxy	10
3.2.14	sip presence outbound proxy port	10
3.2.15	sip presence user name	10
3.2.16	sip presence server user name	10
3.2.17	sip presence server user password	10
3.2.18	sip presence user password save	11
3.2.19	sip Local port	11
3.2.20	sip Transport Protocol	11
3.2.21	sip srtp mode	11
3.2.22	sips trusted certificates	12
3.2.23	tls validate certificates	12
3.2.24	sip registration timeout retry timer	12
3.2.25	sip uri dial direct	12
3.2.26	sip uri dial direct exclusion domain list	13
3.2.27	tos rtP	13

---

3.2.28	tos rtp video	13
3.2.29	tos sip	13
3.2.30	sip rtp port	14
3.2.31	sip rtp port range	14
3.2.32	sip rtp video port	14
3.2.33	sip rtp video port range	14
3.2.34	msrp message timeout	14
3.2.35	update url	15
3.2.36	update user name	15
3.2.37	update user password	15
3.2.38	update interval	15
3.2.39	last update check	16
3.2.40	update local	16
3.3	CTI Server Settings	16
3.3.1	cti server	16
3.3.2	cti server port	16
3.3.3	cti secondary server	17
3.3.4	cti secondary server port	17
3.3.5	cti extension	17
3.3.6	cti pbx	17
3.4	Licensing Settings	17
3.4.1	x aastr a id model	17
3.4.2	x aastr a id options	18
3.5	Client Features	18
3.5.1	sip display name	18
3.5.2	sip screen name	18
3.5.3	sip vmail	18
3.5.4	language	19
3.5.5	telephony codecs	19
3.5.6	default media type	19
3.5.7	max h264 rx rate	20
3.5.8	max h264 tx rate	20
3.5.9	video quality	20
3.5.10	video disabled	20
3.5.11	im disabled	21
3.5.12	call transfer feature code	21
3.5.13	call conference feature code	21
3.5.14	sip dtmf feature code	21
3.5.15	sip dtmf method	21
3.5.16	sip ignore status code	22
3.5.17	call channel type	22
3.5.18	hotkey click2dial	22
3.5.19	hotkey endcall	22
3.5.20	visual enhancement	23
3.5.21	do not confirm client closing	23
3.5.22	external cmd <n>	23
3.5.23	external cmd hotkey <n>	23
3.5.24	external cmd parameter <n>	23
3.5.25	web url <n>	24
3.5.26	web name <n>	24
3.5.27	web type <n>	24
3.6	Telephony Features	25
3.6.1	telephony automatic echo cancellation	25
3.6.2	telephony automatic gain control	25
3.6.3	telephony sound file busy	25
3.6.4	telephony sound file calling	25
3.6.5	telephony sound file ringing	25
3.6.6	feature code <n>	26
3.6.7	feature name <n>	26
3.6.8	enable feature configuration	26
3.7	Number Translation	26

---

3.7.1	number translation enable	26
3.7.2	number translation new country code	26
3.7.3	number translation home area code	27
3.7.4	number translation home country code	27
3.7.5	number translation international feature code	27
3.7.6	number translation long distance feature code	27
3.7.7	number translation trunk feature code	27
3.7.8	number translation minimum digits	28
3.7.9	number translation number format	28
3.7.10	number translation trunk exceptions <n>	28
3.7.11	number translation extension length	28
3.7.12	number translation internal prefixes <n>	28
3.8	General Directory Settings	29
3.8.1	directory outlook enabled	29
3.8.2	directory outlook profile	29
3.8.3	directory cache update interval	29
3.8.4	directory cache delete interval	29
3.8.5	reset image cache	29
3.9	LDAP Directories	30
3.9.1	Ldap <n> name	30
3.9.2	Ldap <n> server	30
3.9.3	Ldap <n> version	30
3.9.4	Ldap<n> base dn	31
3.9.5	Ldap<n> field department search	31
3.9.6	Ldap<n> activedirectory	31
3.9.7	Ldap<n> field id	31
3.9.8	Ldap<n> search filter	32
3.9.9	Ldap<n> field last modified	32
3.9.10	Ldap<n> max time variance	32
3.9.11	Ldap<n> image server uri	32
3.9.12	Ldap<n> picture extension	32
3.9.13	Ldap<n> first name attribute list	33
3.9.14	Ldap<n> last name attribute list	33
3.9.15	Ldap<n> job title attribute list	33
3.9.16	Ldap<n> employee id attribute list	33
3.9.17	Ldap<n> business phone 1 attribute list	33
3.9.18	Ldap<n> mobile phone attribute list	34
3.9.19	Ldap<n> home phone 1 attribute list	34
3.9.20	Ldap<n> other phone attribute list	34
3.9.21	Ldap<n> business fax attribute list	34
3.9.22	Ldap<n> pager attribute list	34
3.9.23	Ldap<n> email 1 attribute list	35
3.9.24	Ldap<n> web address attribute list	35
3.9.25	Ldap<n> company attribute list	35
3.9.26	Ldap<n> room number attribute list	35
3.9.27	Ldap<n> business street attribute list	35
3.9.28	Ldap<n> business postal code attribute list	36
3.9.29	Ldap<n> business city attribute list	36
3.9.30	Ldap<n> business state attribute list	36
3.9.31	Ldap<n> business country attribute list	36
3.9.32	Ldap<n> home street attribute list	36
3.9.33	Ldap<n> home postal code attribute list	37
3.9.34	Ldap<n> home city attribute list	37
3.9.35	Ldap<n> home state attribute list	37
3.9.36	Ldap<n> home country attribute list	37
3.10	Mitel 5000 Directories	38
3.10.1	A5000<n> name	38
3.10.2	A5000<n> server	38
3.10.3	A5000<n> multi-site	38
3.10.4	A5000<n> multi-site name	38
3.10.5	A5000<n> field id	39

---

3.10.6	A5000<n> field last modified	39
3.10.7	A5000<n> max time variance	39
3.10.8	A5000<n> image server uri	39
3.10.9	A5000<n> picture extension	39
3.11	Logging	40
3.11.1	log module sip	40
3.11.2	log module user interface	40
3.11.3	max log files	40
3.12	Error Reporting	41
3.12.1	upload system info email	41
3.12.2	upload system info email method	41
3.12.3	upload system info smtp server	41
3.12.4	upload system info smtp server port	41
3.12.5	upload system info smtp encryption	42
3.12.6	upload system info smtp auth enabled	42
3.12.7	upload system info smtp auth name	42
3.12.8	upload system info smtp auth password	42

# 1 INTRODUCTION

This document describes the configuration parameters used in the system, model and user specific configuration files of BluStar client.

## 1.1 CONFIGURATION FILES LOCAL STORAGE LOCATION

The configuration files are stored within the %APPDATA% folder of the current Windows user:

Win 7/8: %APPDATA%\Roaming\Aastra\BluStar

## 1.2 SYSTEM CONFIGURATION FILE (AASTRA.CFG)

The system configuration file is either provided during installation of the client or downloaded from the configuration server after the user has provided appropriate login credentials and a configuration server URI.

The local file is modified with user name, password and configuration server URI (if available) as entered by the user. The rest of the settings are overwritten with contents from the downloaded system configuration file, if available.

## 1.3 MODEL CONFIGURATION FILE (BSCPC.CFG)

The model specific configuration file contains client settings that either serve as defaults for user-definable settings or which are proprietary for BluStar for PC. It is provided by the configuration server only and is therefore not present on clients that do not use a configuration server.

## 1.4 USER READ-ONLY CONFIGURATION FILE (BSCPC\_<USER>.CFG)

This file contains read-only user specific settings that are to be shared across all BluStar for PC clients the respective user uses, regardless of the physical PC each client runs on. The file is linked to the user by the user login ID <user> being part of the filename.

The file is provided by the configuration server only and is therefore not present on clients that do not use a configuration server.

On start up, the client will try to retrieve the file from the configuration server. If successful, the local file will be replaced by the downloaded file.

## 1.5 USER CONFIGURATION FILE (BSCPC\_<USER>\_LOCAL.CFG)

This file contains user specific settings which were defined by the user and which are to be shared across all BluStar for PC clients the respective user uses, regardless of the physical PC each client runs on. The file is linked to the user by the user login ID <user> being part of the filename.

The file is uploaded to the configuration server after changes to user defined settings.

Note: upload of user specific files is not supported for MiVoice 5000

On startup, the client will try to retrieve the file from the configuration server. If successful, the local file will be replaced by the downloaded file.

## **1.6 USER PREFERENCES FILE (BSCPC\_PREFS\_<USER>.CFG)**

This file is an extension of the user configuration file BSCpc\_<user>.cfg, containing complex data (contacts, call history entries, directory images) in compressed XML format. It is handled in the same way as the user configuration file.

Due to possible large file size, down- and upload can be prevented if necessary in order to save configuration server disk space.

Note: upload of user specific files is not supported for MiVoice 5000

## **1.7 USER LOCAL PREFERENCES FILE (BSCPC\_MYPREFERENCES\_<USER>.CFG)**

The local preferences file contains user defined, workstation-dependent settings (audio/video devices settings, window positions on screen, etc.) that cannot be shared across different PCs.

This file is not down- or uploaded but only stored locally. The contents of this file are not subject of this documentation as they are not intended to be changed directly by administrators or users.

## **1.8 ORDER OF PRECEDENCE**

System and model settings are predefined by an administrator and cannot be changed by the user. However, user defined settings can override corresponding system and model defaults.

In general, any configuration file from aastral.cfg to BSCpc\_<user>.cfg can contain any setting. However, if a setting occurs in multiple files, it is considered in a bottom-up priority order, ignoring further occurrences in the other files:

BSCpc\_<user>\_local.cfg overrides BSCpc\_<user>.cfg overrides  
BSCpc.cfg overrides aastral.cfg

## **1.9 PARAMETER LOCKING AND PARAMETER OVERRIDING**

### **1.9.1 PARAMETER LOCKING**

The exclamation mark character (“!”) can be prefixed to a parameter name in order to mark it as locked, i. e. the user will not be able to change it. GUI elements for the manipulation of locked parameters will be disabled.

If a parameter is locked in one of the configuration files, it is considered locked for all files, even if a higher ranking file in the order of precedence (see 1.8 Order of precedence) contains the same parameter in unlocked state.

Example:     !configuration server uri : http://blustar.acme.com

### 1.9.2    **PARAMETER OVERRIDING**

Parameter overriding is indicated by the caret character (“^”) and has an effect only on user configuration files. A parameter marked in this way will overwrite the values of other occurrences of the same parameter of higher order of precedence (see 1.8 Order of precedence) in the user files. However, the overridden parameters will not be deleted from the affected file(s).

Example:     ^configuration server uri : http://blustar.acme.com

## 2 LOG FILES

The BluStar client logs its activities in 3 categories of files

- “BluStar\_<yyymm>.log”
- “MSRP\_<yyymm>.log“
- “sipLog.txt” / “sipLog1.txt”

The log files are located in the directory: %LOCALAPPDATA%\Aastra\BluStar\Log  
(Windows 7/8)

### 2.1 LOG FILES “BLUSTAR\_<YYMMTT>.LOG“ AND “MSRP\_<YYMMTT>.LOG“

- The BluStar application creates one log file each for every day
- The BluStar application deletes log files older than 4 days on application start (only)
- The log level can be adjusted using the configuration file parameter <log module user interface>
  - The default value of <log module user interface> is “6”
  - The maximum value of <log module user interface> is “9”
  - If the option “Detailed logging” in the configuration dialog is not checked (“General → Advanced → Maintenance”) the value of the parameter <log module user interface> is decreased to “3”. Note that “Detailed logging” is “on” by default.

### 2.2 LOG FILES “SIPLOG.TXT“ AND “SIPLOG1.TXT“

- The BluStar application checks if the file „sipLog.txt“ is larger than 8 MB on start-up and every 20 minutes. If the file is larger than 8 MB further logging information is written to the file „sipLog1.txt“
- If the file „sipLog1.txt“ exceeds 8 MB the logging changes back to the file „sipLog.txt“ which will be deleted before writing new information
- So the total file size of both “sipLog.txt“ and “sipLog1.txt“ will not exceed 16 MB (temporarily it may exceed this value a little bit when switching between both files)
- The log level can be adjusted using the configuration file parameter <log module sip>
  - The default value of <log module sip> is “3”
  - The maximum value of <log module sip> is “9”
  - If the option “Detailed logging” in the configuration dialog is not checked (“General → Advanced → Maintenance”) the value of the parameter <log module sip> is decreased to “0”. Note that “Detailed logging” is “on” by default.

# 3 CONFIGURATION PARAMETERS

## 3.1 CONFIGURATION SERVER SETTINGS

### 3.1.1 CONFIG USER NAME

<b>Description</b>	User name for configuration server if retrieval of configuration files is accomplished via HTTP or FTP
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.1.2 CONFIG PASSWORD

<b>Description</b>	User's login password for configuration server
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.1.3 FORCE CONFIG URL CREDENTIALS

<b>Description</b>	Force usage of provided inline authentication credentials also for client/user configuration files
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 or 1
<b>Default value</b>	0

### 3.1.4 CONFIGURATION SERVER URI

<b>Description</b>	Configuration server for client/user configuration files
<b>Recommended in</b>	astra.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	Full URL including protocol identifier and directory path
<b>Default value</b>	(none)
<b>Remark</b>	<ul style="list-style-type: none"> <li>• If <b>user config url</b> is defined, user configuration files will be retrieved from/uploaded to the location indicated there</li> <li>• The supported protocols are FTP and HTTP</li> </ul>

<b>Remark for FTP</b>	<p>FTP URLs can use inline authentication credentials:  <code>ftp://&lt;ftp username&gt;:&lt;ftp password&gt;@&lt;server&gt;</code></p> <p>The inline credentials are used to load global configuration files <code>&lt;astra.cfg&gt;</code> and <code>&lt;BSCpc.cfg&gt;</code>.</p> <p>The inline credentials interfere with the client's user login credentials in the following way:</p> <ul style="list-style-type: none"> <li>• <i>FTP credentials defined and no user login password entered:</i> FTP credentials are used for login to configuration server</li> <li>• <i>user login credentials available:</i> FTP credentials are ignored</li> <li>• <i>user login password missing and no FTP credentials:</i> anonymous FTP login</li> </ul>
-----------------------	---

### 3.1.5 USER CONFIG URL

<b>Description</b>	Storage location of user configuration files if different from system and model configuration file location
<b>Recommended in</b>	<code>BSCpc.cfg</code>
<b>Data type</b>	String
<b>Value range</b>	Full URL including protocol identifier and directory path
<b>Default value</b>	(none)
<b>Remark</b>	<ul style="list-style-type: none"> <li>• If not defined, the user configuration files will be retrieved from/uploaded to the location defined by configuration server uri</li> <li>• The supported protocols are FTP and HTTP</li> </ul>

### 3.1.6 HTTPS VALIDATE CERTIFICATES

<b>Description</b>	Defines whether a server certificate is to be validated when using an SSL connection
<b>Recommended in</b>	<code>astra.cfg</code>
<b>Data type</b>	Integer
<b>Value range</b>	0 (no), 1 (yes)
<b>Default value</b>	1
<b>Remark</b>	<ul style="list-style-type: none"> <li>• If set to 0, an invalid or missing certificate will be ignored and the client will continue with authentication and configuration file download.</li> <li>• If set to 1 (default) and the certificate is invalid or missing, the client will not authenticate towards the configuration server and will not download configuration files. Further download attempts will be discarded.</li> </ul>

### 3.1.7 USER CONFIG UPLOAD

<b>Description</b>	Defines the interval (in seconds) for checking whether changes in configuration files occurred. In case of changes, an upload to the configuration server is triggered.
<b>Recommended in</b>	<code>astra.cfg</code> , <code>BSCpc.cfg</code> , <code>BSCpc_&lt;user&gt;.cfg</code>
<b>Data type</b>	Integer
<b>Value range</b>	0 - 16400
<b>Default value</b>	3600 (1 hr)
<b>Remark</b>	<ul style="list-style-type: none"> <li>• A value of 0 disables the periodic check. Configuration files are then uploaded to the configuration server only when the client is being closed.</li> <li>• Values beyond the defined value range result in the default value becoming effective.</li> </ul>

### 3.1.8 DISABLE USER PREFERENCES FILE TRANSFER

<b>Description</b>	Indicates whether BSCpc_prefs_<user>.cfg shall be downloaded from and uploaded to the configuration server
<b>Recommended in</b>	aatra.cfg, BSCpc.cfg
<b>Data type</b>	Boolean (string or integer representation)
<b>Value range</b>	True (1), False (0)
<b>Default value</b>	False
<b>Remark</b>	Set the value to <i>False</i> if large file size has negative impact on configuration server performance or disk space.

### 3.1.9 FORCE AUTOMATIC CONFIGURATION

<b>Description</b>	Forcing automatic configuration file handling for the client
<b>Recommended in</b>	aatra.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 or 1
<b>Default value</b>	0
<b>Remark</b>	Setting the value to 1 will disable the checkbox “Automatic configuration” in the Options dialog.

## 3.2 SERVER, SIP AND SERVICES CONNECTION SETTINGS

### 3.2.1 SIP USER NAME

<b>Description</b>	SIP login user name as required by the PBX (can be directory/Windows user name, extension number, etc.)
<b>Recommended in</b>	(aatra.cfg,) BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Also stored in aatra.cfg if <b>config user name</b> is not explicitly defined

### 3.2.2 SIP PASSWORD

<b>Description</b>	User's login password for PBX
<b>Recommended in</b>	(aatra.cfg,) BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Must not be encrypted on the configuration server side Also stored in aatra.cfg if <b>config password</b> is not explicitly defined

### 3.2.3 SIP PROXY IP

<b>Description</b>	SIP proxy (call manager) IP address/host name
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	When using TLS/SRTP ( <b>sip transport protocol : 4</b> ) you have to use the FQDN of the call manager as it is used in the certificate

### 3.2.4 SIP PROXY PORT

<b>Description</b>	SIP proxy (call manager) port
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	5060
<b>Remark</b>	When using TLS/SRTP ( <b>sip transport protocol : 4</b> ) the value needs to be changed accordingly (most likely to 5061)

### 3.2.5 SIP BACKUP PROXY IP

<b>Description</b>	Backup SIP proxy (call manager) IP address/host name
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.2.6 SIP BACKUP PROXY PORT

<b>Description</b>	Backup SIP proxy (call manager) port
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	5060

### 3.2.7 SIP OUTBOUND PROXY

<b>Description</b>	Outbound SIP proxy IP address/host name
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.2.8 SIP OUTBOUND PROXY PORT

<b>Description</b>	Outbound SIP proxy port
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	5060

### 3.2.9 SIP BACKUP OUTBOUND PROXY

<b>Description</b>	Backup outbound SIP proxy IP address/host name
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.2.10 SIP BACKUP OUTBOUND PROXY PORT

<b>Description</b>	Backup outbound SIP proxy port
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	5060

### 3.2.11 SIP PRESENCE SERVER

<b>Description</b>	BluStar Server IP address/host name
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.2.12 SIP PRESENCE PORT

<b>Description</b>	BluStar Server port
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	5060

### 3.2.13 SIP PRESENCE OUTBOUND PROXY

<b>Description</b>	BluStar Server outbound proxy IP address/host name
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.2.14 SIP PRESENCE OUTBOUND PROXY PORT

<b>Description</b>	BluStar Server outbound SIP proxy port
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	5060

### 3.2.15 SIP PRESENCE USER NAME

<b>Description</b>	User's e-mail address as used by the Presence Server to uniquely identify the user.
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	Valid e-mail address
<b>Default value</b>	(none)

### 3.2.16 SIP PRESENCE SERVER USER NAME

<b>Description</b>	Active Directory user name used to authenticate the user to the Presence Server
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(currently logged on Windows user name)

### 3.2.17 SIP PRESENCE SERVER USER PASSWORD

<b>Description</b>	Active Directory password used to authenticate the user to the Presence Server
<b>Recommended in</b>	BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.2.18 SIP PRESENCE USER PASSWORD SAVE

<b>Description</b>	Indicates whether the <b>sip presence user password</b> is to be saved to file for permanent use, or if the user is to be prompted for it on each client launch again
<b>Recommended in</b>	aatra.cfg, BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 (no), 1 (yes)
<b>Default value</b>	1 (yes)

### 3.2.19 SIP LOCAL PORT

<b>Description</b>	Local port for SIP connections
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	0
<b>Remark</b>	With value 0 a random port between 49152 and 65535 will be used.

### 3.2.20 SIP TRANSPORT PROTOCOL

<b>Description</b>	SIP transport protocol
<b>Recommended in</b>	aatra.cfg, BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	Enumeration (Integer)
<b>Value range</b>	0 = UDP or TCP 1 = UDP 2 = TCP <b>4 = TLS</b>
<b>Default value</b>	0
<b>Remark</b>	If the parameter value is 0, UDP is used in the first place. If UDP fails, the client automatically switches to TCP.

### 3.2.21 SIP SRTP MODE

<b>Description</b>	Enable / force using SRTP for audio (SRTP for video is not supported)
<b>Recommended in</b>	aatra.cfg, BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 = SRTP disabled <b>1 = SRTP preferred</b> 2 = SRTP only – will not serve non-SRTP connections
<b>Default value</b>	0

### 3.2.22 SIPS TRUSTED CERTIFICATES

<b>Description</b>	URL where the certificate for validation of the call server will be downloaded from. Supported protocols: ftp, http, https
<b>Recommended in</b>	astra.cfg, BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	sftp is not supported, https is recommended. Example: <code>ftp://ftp:sesam123!@10.103.173.66/commxone-CA.pem</code>

### 3.2.23 TLS VALIDATE CERTIFICATES

<b>Description</b>	Defines whether a server certificate is to be validated when using an TLS connection
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 (no), 1 (yes)
<b>Default value</b>	1
<b>Remark</b>	If set to 0, an invalid or missing certificate will be ignored and the client will continue.

### 3.2.24 SIP REGISTRATION TIMEOUT RETRY TIMER

<b>Description</b>	SIP session duration (in seconds)
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	(not defined)
<b>Default value</b>	3600

### 3.2.25 SIP URI DIAL DIRECT

<b>Description</b>	Enable or disable direct dialing to SIP URI targets. If enabled, the device will dial directly to the SIP URI target. Otherwise, if disabled, the device will dial via the PBX.
<b>Recommended in</b>	astra.cfg, BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 (disabled), 1 (enabled)
<b>Default value</b>	1

### 3.2.26 SIP URI DIAL DIRECT EXCLUSION DOMAIN LIST

<b>Description</b>	Defines an exclusion list of domains which have to be dialed via the PBX. Only applicable with <sip uri dial direct : 1>.
<b>Recommended in</b>	aatra.cfg, BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	String
<b>Value range</b>	List of domains, separated by semicolon
<b>Default value</b>	(none)

### 3.2.27 TOS RTP

<b>Description</b>	Differentiated Services Code Point (DSCP) for audio RTP packets
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String: Hexadecimal number prepended by "0x" - or - Integer value
<b>Value range</b>	0-255
<b>Default value</b>	Hex: 0x00 / Int: 0
<b>Remark</b>	Application-controlled DSCP is deprecated since Windows 7. DSCP must be set by local or global QoS group policy instead.

### 3.2.28 TOS RTP VIDEO

<b>Description</b>	Differentiated Services Code Point (DSCP) for video RTP packets
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String: Hexadecimal number prepended by "0x" - or - Integer value
<b>Value range</b>	0-255
<b>Default value</b>	Hex: 0x00 / Int: 0
<b>Remark</b>	Application-controlled DSCP is deprecated since Windows 7. DSCP must be set by local or global QoS group policy instead.

### 3.2.29 TOS SIP

<b>Description</b>	Differentiated Services Code Point (DSCP) for SIP packets
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String: Hexadecimal number prepended by "0x" - or - Integer value
<b>Value range</b>	0-255
<b>Default value</b>	Hex: 0x00 / Int: 0
<b>Remark</b>	Application-controlled DSCP is deprecated since Windows 7. DSCP must be set

by local or global QoS group policy instead.

### 3.2.30 SIP RTP PORT

<b>Description</b>	Port range base for RTP audio transmissions
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535) Must be an even number
<b>Default value</b>	40000
<b>Remark</b>	The size of the port range is defined by <b>sip rtp port range</b>

### 3.2.31 SIP RTP PORT RANGE

<b>Description</b>	Size of the port range for RTP audio transmissions
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	n/a
<b>Default value</b>	2000

### 3.2.32 SIP RTP VIDEO PORT

<b>Description</b>	Port range base for RTP video transmissions
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535) Must be an even number
<b>Default value</b>	40000
<b>Remark</b>	The size of the port range is defined by <b>sip rtp video port range</b>

### 3.2.33 SIP RTP VIDEO PORT RANGE

<b>Description</b>	Size of the port range for RTP video transmissions
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	n/a
<b>Default value</b>	2000

### 3.2.34 MSRP MESSAGE TIMEOUT

<b>Description</b>	Timeout for an MSRP message after which the contacted client is considered unreachable (in milliseconds)
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	None

---

<b>Default value</b>	10000
<b>Remark</b>	A message will be displayed and the MSRP session will be closed.

### 3.2.35 UPDATE URL

<b>Description</b>	Source directory for client updates. Can be a local directory, network share, or HTTP/HTTPS URL
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	When using a SSL connection, parameter <b>https validate certificate</b> might be required, depending on the provided certificate.

### 3.2.36 UPDATE USER NAME

<b>Description</b>	User name for client update download authentication when <b>update url</b> is a web URL
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.2.37 UPDATE USER PASSWORD

<b>Description</b>	User password for client update download authentication when <b>update url</b> is a web URL
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Password needs to be encrypted by the configuration server.

### 3.2.38 UPDATE INTERVAL

<b>Description</b>	Interval (in days) for checking for the availability of a new client update
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	Integer
<b>Value range</b>	>= -1
<b>Default value</b>	-1 (disabled)
<b>Remark</b>	-1: check for updates disabled 0: check for updates on each client launch > 0: check for updates every <n> days Parameter <b>last update check</b> defines the base for the calculation for when the next check is due.

### 3.2.39 LAST UPDATE CHECK

<b>Description</b>	Date and time of the last check for availability of client updates
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	String (date and time representation)
<b>Value range</b>	(a valid date and time value)
<b>Default value</b>	01.01.2000
<b>Remark</b>	The value gets modified by the client after each check for updates in local astra.cfg. This parameter is not intended to be preset by a configuration server based definition.

### 3.2.40 UPDATE LOCAL

<b>Description</b>	Indicates if a previously downloaded, but not yet installed, update package is locally available for installation. This setting only applies to update packages downloaded from a web resource.
<b>Recommended in</b>	astra.cfg
<b>Data type</b>	Boolean (integer representation)
<b>Value range</b>	0 (not available), 1 (available)
<b>Default value</b>	0 (not available)
<b>Remark</b>	The value gets modified by the client in local astra.cfg according to the user's choice after a remotely available update was downloaded. This parameter is not intended to be preset by a configuration server based definition.

## 3.3 CTI SERVER SETTINGS

### 3.3.1 CTI SERVER

<b>Description</b>	CTI server IP address or host name
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.3.2 CTI SERVER PORT

<b>Description</b>	CTI server port
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	5070

### 3.3.3 CTI SECONDARY SERVER

<b>Description</b>	Backup CTI server IP address or host name
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.3.4 CTI SECONDARY SERVER PORT

<b>Description</b>	Backup CTI server port
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (1024-65535)
<b>Default value</b>	5070

### 3.3.5 CTI EXTENSION

<b>Description</b>	User's extension number on CTI server
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.3.6 CTI PBX

<b>Description</b>	PBX link number to start <cti extension> on
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	Numerical value > 0
<b>Default value</b>	1

## 3.4 LICENSING SETTINGS

These parameters are used as part of the X-Aastra-Id header during SIP registration to allow Mitel equipment to correctly identify the clients.

### 3.4.1 X AASTRA ID MODEL

<b>Description</b>	Identifies the model to be used by the BluStar client. This may depend on the licenses available.	
<b>Recommended in</b>	BSCpc_<user>.cfg	
<b>Data type</b>	String	
<b>Value range</b>	02	(Standard Softphone)
	04	(Video Softphone)

<b>Default value</b>	04
----------------------	----

### 3.4.2 X AASTRA ID OPTIONS

<b>Description</b>	Identifies the option to be used by the BluStar client. This may depend on the licenses available.	
<b>Recommended in</b>	BSCpc_<user>.cfg	
<b>Data type</b>	String	
<b>Value range</b>	01	(Plug-in MS Lync)
	04	(Video)
<b>Default value</b>	04	

## 3.5 CLIENT FEATURES

### 3.5.1 SIP DISPLAY NAME

<b>Description</b>	User name to be displayed in the client GUI	
<b>Recommended in</b>	BSCpc_<user>.cfg	
<b>Data type</b>	String	
<b>Value range</b>	n/a	
<b>Default value</b>	(none)	
<b>Remark</b>	This name is used for display if the user's name could not be found in the local contacts and configured directories.	

### 3.5.2 SIP SCREEN NAME

<b>Description</b>	User name to be displayed in the client GUI	
<b>Recommended in</b>	BSCpc_<user>.cfg	
<b>Data type</b>	String	
<b>Value range</b>	n/a	
<b>Default value</b>	(none)	
<b>Remark</b>	This name is used for display in the caption, if not set <sip display name> or <sip user name> will be displayed.	

### 3.5.3 SIP VMAIL

<b>Description</b>	User's voice mail number	
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg	
<b>Data type</b>	String	
<b>Value range</b>	n/a	
<b>Default value</b>	(none)	

### 3.5.4 LANGUAGE

<b>Description</b>	Client language
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	Valid ISO 2-letter language name abbreviation: de (German) en (English) es (Spanish) fr (French) it (Italian) nl (Dutch) pt-BR (Brazil) ru (Russian) sv (Swedish) (none) - use current operating system language if one of the above, else "en" (English) is used automatically
<b>Default value</b>	(none) = currently set operating system language if supported, else English

### 3.5.5 TELEPHONY CODECS

<b>Description</b>	List of available telephony codecs
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String (list of enumeration members)
<b>Value range</b>	Comma-separated list of enumeration members (as string representations):  PCMU PCMA G722 G729AB (only available in local markets) ILBC
<b>Default value</b>	(none)

### 3.5.6 DEFAULT MEDIA TYPE

<b>Description</b>	Defines the standard media type to be used when invoking communication
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String (Enumeration)
<b>Value range</b>	Audio IM Video Email ScreenShare None
<b>Default value</b>	Audio

### 3.5.7 MAX H264 RX RATE

<b>Description</b>	Video stream reception (downstream) maximum allowed bitrate, in 1000 bit/s
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	128, 384, 768, 2304
<b>Default value</b>	2304
<b>Remark</b>	Overridden by <b>video max kbitrate</b> if defined Overrides bitrate defined by <b>video quality</b> and limits the selection of available video modes to those that use a less or equal bitrate Applies both to LAN and wireless settings

### 3.5.8 MAX H264 TX RATE

<b>Description</b>	Video stream transmission (upstream) maximum allowed bitrate, in 1000 bit/s
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	128, 384, 768, 2304
<b>Default value</b>	2304
<b>Remark</b>	Overridden by <b>video max kbitrate</b> if defined Overrides bitrate defined by <b>video quality</b> and limits the selection of available video modes to those that use a less or equal bitrate Applies both to LAN and wireless settings

### 3.5.9 VIDEO QUALITY

<b>Description</b>	Video stream resolution, framerate and bitrate
<b>Recommended in</b>	astra.cfg, BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Enumeration (String representation)
<b>Value range</b>	Q160x90f30 (160x90 px, 30 fps, 128000 kbit/s) Q320x180f30 (320x180 px, 30 fps, 384000 kbit/s) Q640x360f30 (640x360 px, 30 fps, 768000 kbit/s) Q1280x720f30 (1280x720 px, 30 fps, 2304000 kbit/s)
<b>Default value</b>	Q640x360f30
<b>Remark</b>	The bitrate is overridden by <b>max h264 tx rate</b> if defined

### 3.5.10 VIDEO DISABLED

<b>Description</b>	Disable all video functionality
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer (Boolean)

---

<b>Value range</b>	0 (false), 1 (true)
<b>Default value</b>	0 (enabled)

### 3.5.11 IM DISABLED

<b>Description</b>	Disable all IM functionality
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer (Boolean)
<b>Value range</b>	0 (false), 1 (true)
<b>Default value</b>	0 (enabled)

### 3.5.12 CALL TRANSFER FEATURE CODE

<b>Description</b>	Access code for call transfers
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.5.13 CALL CONFERENCE FEATURE CODE

<b>Description</b>	Access code for conferences
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.5.14 SIP DTMF FEATURE CODE

<b>Description</b>	Access code (digit) for DTMF dialing mode
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.5.15 SIP DTMF METHOD

<b>Description</b>	Type of DTMF tone to be used
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Enumeration (String or integer)
<b>Value range</b>	Info 0 PCM 1 (not used) RFC2833 2
<b>Default value</b>	0
<b>Remark</b>	Value PCM (1) is not used with BSC.

### 3.5.16 SIP IGNORE STATUS CODE

<b>Description</b>	Defines the response code that the client sends when rejecting a call	
<b>Recommended in</b>	aastra.cfg, BSCpc.cfg	
<b>Data type</b>	Integer	
<b>Value range</b>	603	(rejected)
	486	(busy)
<b>Default value</b>	603	

### 3.5.17 CALL CHANNEL TYPE

<b>Description</b>	Defines the channel type used for communication	
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg	
<b>Data type</b>	String (Enumeration)	
<b>Value range</b>	SIP	
	CSTA	
	SIP_8000i	
	CSTA_8000i	
<b>Default value</b>	SIP	

### 3.5.18 HOTKEY CLICK2DIAL

<b>Description</b>	Defines the global hotkey for dialing a number from a selected text in any application	
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg	
<b>Data type</b>	String	
<b>Value range</b>	Modifier key(s) and key in the format <Modifier(s)>:<Key> Represented as numeric (enumeration) values. Modifier keys: Control        2 Shift         4 Control and Shift modifier can be combined by addition of their respective numeric value. For the key codes, the enumeration of System.Windows.Forms.Keys in .NET Framework does apply.	
	<i>Examples:</i> D0 – D9: 48 – 57 A – Z: 65 – 90 F1 – F12: 112 – 123	
<b>Default value</b>	(none)	

### 3.5.19 HOTKEY ENDCALL

<b>Description</b>	Defines the global hotkey for ending a call	
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg	
<b>Data type</b>	String	
<b>Value range</b>	n/a	
<b>Default value</b>	None	

### 3.5.20 VISUAL ENHANCEMENT

<b>Description</b>	Enable or disable visual aid for the presence color status bar. User will be able to differentiate the status by color and/or icon.
<b>Recommended in</b>	astra.cfg, BSCpc.cfg, BSCpc_<user>.cfg , BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 (disabled), 1 (enabled)
<b>Default value</b>	0

### 3.5.21 DO NOT CONFIRM CLIENT CLOSING

<b>Description</b>	Defines whether the user is to be prompted for confirmation when he closes the client
<b>Recommended in</b>	BSCpc_<user>_local.cfg
<b>Data type</b>	Boolean (String representation)
<b>Value range</b>	True, False
<b>Default value</b>	False (show message prompt)

### 3.5.22 EXTERNAL CMD <N>

<b>Description</b>	Command to call an external application via hotkey
<b>Recommended in</b>	BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.5.23 EXTERNAL CMD HOTKEY <N>

<b>Description</b>	Hotkey to call an external application
<b>Recommended in</b>	BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

More information about possible values can be found under <hotkey click2dial>

### 3.5.24 EXTERNAL CMD PARAMETER <N>

<b>Description</b>	Optional parameter for external application call
<b>Recommended in</b>	BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

Example for calling external commands via a hotkey (the tag <ANUM\_CLIP> can be used during an offered or established incoming call to be replaced by the clip of the remote party):

```
external cmd 1 : C:\Program Files\Aastra\test.bat
external cmd 2 : www.google.de/search?q=EXTERNAL_CMD_PARAM
external cmd 3 : notepad.exe ANUM_CLIP.txt
external cmd hotkey 1 : 2:121
external cmd hotkey 2 : 6:121
external cmd hotkey 3 : 6:120
external cmd param 2 : ptest
```

### 3.5.25 WEB URL <N>

<b>Description</b>	URL to be displayed in the integrated web panel
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.5.26 WEB NAME <N>

<b>Description</b>	Display name for the URL to be displayed in the integrated web panel
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.5.27 WEB TYPE <N>

<b>Description</b>	Defines whether the URL will be displayed in the integrated web panel or launched by the default web browser
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	Integer
<b>Value range</b>	1 or 2
<b>Default value</b>	1 (integrated web panel)

Example for usage of web URLs (the tag <ANUM\_CLIP> can be used during an offered or established call to be replaced by the clip of the remote party):

```
web name 1 : Aastra
web name 2 : Mitel
web name 3 : Google
web name 4 : BluStar Web
web type 3 : 2
web url 1 : www.aastracom
web url 2 : www.mitel.com
web url 3 : www.google.de/search?q=ANUM\_CLIP
web url 4 : sebsw.aastracom/bswmobile/quickactivities
```

## 3.6 TELEPHONY FEATURES

### 3.6.1 TELEPHONY AUTOMATIC ECHO CANCELLATION

<b>Description</b>	Enables automatic echo cancellation for all audio output devices
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Boolean (String representation)
<b>Value range</b>	True (enabled), False (disabled)
<b>Default value</b>	True

### 3.6.2 TELEPHONY AUTOMATIC GAIN CONTROL

<b>Description</b>	Enables automatic gain control for all audio input devices
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Boolean (String representation)
<b>Value range</b>	True (enabled), False (disabled)
<b>Default value</b>	False

### 3.6.3 TELEPHONY SOUND FILE BUSY

<b>Description</b>	Sound file for busy signal
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	busyix.wav
<b>Remark</b>	File "busyix.wav" in the client's program folder is intended for this purpose.

### 3.6.4 TELEPHONY SOUND FILE CALLING

<b>Description</b>	Sound file for call signal
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	ringout.wav
<b>Remark</b>	File "ringout.wav" in the client's program folder is intended for this purpose.

### 3.6.5 TELEPHONY SOUND FILE RINGING

<b>Description</b>	Sound file for ringing signal
<b>Recommended in</b>	BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	ringit.wav
<b>Remark</b>	File "ringit.wav" in the client's program folder is intended for this purpose.

### 3.6.6 FEATURE CODE <N>

<b>Description</b>	Feature code or phone number to dial via a button
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	All pbx specific feature codes or phone numbers
<b>Default value</b>	(none)

### 3.6.7 FEATURE NAME <N>

<b>Description</b>	Label of the button to call the feature code
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.6.8 ENABLE FEATURE CONFIGURATION

<b>Description</b>	Allows the user to configure feature code buttons from the GUI if set to 1
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 or 1
<b>Default value</b>	1

## 3.7 NUMBER TRANSLATION

### 3.7.1 NUMBER TRANSLATION ENABLE

<b>Description</b>	Enable number translation
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer (Boolean)
<b>Value range</b>	0 (false), 1 (true)
<b>Default value</b>	0

### 3.7.2 NUMBER TRANSLATION NEW COUNTRY CODE

<b>Description</b>	String to replace country code with
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.7.3 NUMBER TRANSLATION HOME AREA CODE

<b>Description</b>	Area code to be ignored in dialed numbers
<b>Recommended in</b>	aasta.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.7.4 NUMBER TRANSLATION HOME COUNTRY CODE

<b>Description</b>	Country code to be ignored in dialed numbers
<b>Recommended in</b>	aasta.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.7.5 NUMBER TRANSLATION INTERNATIONAL FEATURE CODE

<b>Description</b>	Access code for international calls
<b>Recommended in</b>	aasta.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.7.6 NUMBER TRANSLATION LONG DISTANCE FEATURE CODE

<b>Description</b>	Access code for long distance calls
<b>Recommended in</b>	aasta.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.7.7 NUMBER TRANSLATION TRUNK FEATURE CODE

<b>Description</b>	Trunk access code for external calls
<b>Recommended in</b>	aasta.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.7.8 NUMBER TRANSLATION MINIMUM DIGITS

<b>Description</b>	Maximum (!) number of digits of internal numbers
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	n/a
<b>Default value</b>	0

### 3.7.9 NUMBER TRANSLATION NUMBER FORMAT

<b>Description</b>	Type of dialing plan used for number translation
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Enumeration (Integer)
<b>Value range</b>	Standard 0 Tapi 1 NorthAmerican 2
<b>Default value</b>	0

### 3.7.10 NUMBER TRANSLATION TRUNK EXCEPTIONS <N>

<b>Description</b>	Element of a list of number prefixes not requiring a trunk access code
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Multiple list items possible, <n> is the consecutively numbered element index starting with 1

### 3.7.11 NUMBER TRANSLATION EXTENSION LENGTH

<b>Description</b>	Number of digits for internal extension
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	n/a
<b>Default value</b>	0

### 3.7.12 NUMBER TRANSLATION INTERNAL PREFIXES <N>

<b>Description</b>	Element of a list of number prefixes that can be added to an internal extension number to define an external phone number
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Multiple list items possible, <n> is the consecutively numbered element index starting with 1

## 3.8 GENERAL DIRECTORY SETTINGS

### 3.8.1 DIRECTORY OUTLOOK ENABLED

<b>Description</b>	Enables use of Outlook directory
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Boolean (String representation)
<b>Value range</b>	True, False
<b>Default value</b>	True

### 3.8.2 DIRECTORY OUTLOOK PROFILE

<b>Description</b>	Outlook directory profile name
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.8.3 DIRECTORY CACHE UPDATE INTERVAL

<b>Description</b>	Interval for updating directory cache (in seconds)
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	>= 0
<b>Default value</b>	86400 (1 day)

### 3.8.4 DIRECTORY CACHE DELETE INTERVAL

<b>Description</b>	Interval for deleting the directory cache (in milliseconds)
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	>= 0
<b>Default value</b>	900

### 3.8.5 RESET IMAGE CACHE

<b>Description</b>	With this parameter set to 1 the local image cache can be forced to be deleted on every client shutdown.
<b>Recommended in</b>	BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 or 1
<b>Default value</b>	0

## 3.9 LDAP DIRECTORIES

Configuration can contain up to 5 directories. Directory parameters are numbered with the same index number <n> for each directory; the different directories are consecutively numbered starting with 1.

For n = 1, the index number can be omitted, which makes the parameters compatible with 8000i and iOS client settings.

### 3.9.1 LDAP <N> NAME

<b>Description</b>	Directory name displayed in BluStar client
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Shared with 8000i but differing by index number

### 3.9.2 LDAP <N> SERVER

<b>Description</b>	LDAP directory host
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	User ID, password, host name and port combined in the expression <user ID>:<password>@<host name>:<port>
<b>Default value</b>	Port: 389 Others: (none)
<b>Remark</b>	Shared with 8000i but differing by index number. User ID and password are optional. User ID and password (if applicable) need to be encrypted (use Mitel's SeC encryption tool). The directory will be discarded if this parameter is empty.

### 3.9.3 LDAP <N> VERSION

<b>Description</b>	LDAP database version
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid database version number
<b>Default value</b>	3

### 3.9.4 LDAP<N> BASE DN

<b>Description</b>	LDAP search base
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Shared with 8000i but differing by index number.

### 3.9.5 LDAP<N> FIELD DEPARTMENT SEARCH

<b>Description</b>	Specifies the LDAP attribute name to search in for department name
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0 (attribute <department> 1 (attribute <departmentName> 2 (attribute <organizationalUnitName> 3 (attribute <organizationName>
<b>Default value</b>	0

### 3.9.6 LDAP<N> ACTIVEDIRECTORY

<b>Description</b>	Indicates whether directory is an AD directory
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer (Boolean)
<b>Value range</b>	0 (false), 1 (true)
<b>Default value</b>	0

### 3.9.7 LDAP<N> FIELD ID

<b>Description</b>	Specifies the LDAP attribute name of the field to use to uniquely identify the directory items
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	<distinguishedName> (for standard LDAP) <objectGUID> (for Active Directory)

### 3.9.8 LDAP<N> SEARCH FILTER

<b>Description</b>	Overwrites the default LDAP search filter for retrieving all LDAP entries
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(objectClass=person) <i>(for standard LDAP)</i> <i>(&amp;(objectClass=Person)(!(userAccountControl:1.2.840.113556.1.4.803:=2))</i> <i>(!(MSEchHideFromAddressLists=TRUE)) (for Active Directory)</i>

### 3.9.9 LDAP<N> FIELD LAST MODIFIED

<b>Description</b>	Field containing the dataset's last modification date and time
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.9.10 LDAP<N> MAX TIME VARIANCE

<b>Description</b>	Time (in minutes) after which a cached entry is considered outdated
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	n/a
<b>Default value</b>	15

### 3.9.11 LDAP<N> IMAGE SERVER URI

<b>Description</b>	URL to access pictures of users in the LDAP directory
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	A valid URL
<b>Default value</b>	(none)

### 3.9.12 LDAP<N> PICTURE EXTENSION

<b>Description</b>	extension of user picture files
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	A valid image file extension (e. g. jpg, png, etc.) without “.”
<b>Default value</b>	(none)

### 3.9.13 LDAP<N> FIRST NAME ATTRIBUTE LIST

<b>Description</b>	Defines the <i>first name</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	givenName

### 3.9.14 LDAP<N> LAST NAME ATTRIBUTE LIST

<b>Description</b>	Defines the <i>last name</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	sn

### 3.9.15 LDAP<N> JOB TITLE ATTRIBUTE LIST

<b>Description</b>	Defines the <i>job title</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	title

### 3.9.16 LDAP<N> EMPLOYEE ID ATTRIBUTE LIST

<b>Description</b>	Defines the <i>employee ID</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	employeeID

### 3.9.17 LDAP<N> BUSINESS PHONE 1 ATTRIBUTE LIST

<b>Description</b>	Defines the <i>business phone number</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	telephoneNumber

### 3.9.18 LDAP<N> MOBILE PHONE ATTRIBUTE LIST

<b>Description</b>	Defines the <i>mobile phone number</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	mobileTelephoneNumber

### 3.9.19 LDAP<N> HOME PHONE 1 ATTRIBUTE LIST

<b>Description</b>	Defines the <i>home telephone number</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	homePhone

### 3.9.20 LDAP<N> OTHER PHONE ATTRIBUTE LIST

<b>Description</b>	Defines the <i>other telephone number</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	otherTelephone

### 3.9.21 LDAP<N> BUSINESS FAX ATTRIBUTE LIST

<b>Description</b>	Defines the <i>business fax number</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	facsimile

### 3.9.22 LDAP<N> PAGER ATTRIBUTE LIST

<b>Description</b>	Defines the <i>pager number</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	pager

### 3.9.23 LDAP<N> EMAIL 1 ATTRIBUTE LIST

<b>Description</b>	Defines the <i>e-mail address</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	mail

### 3.9.24 LDAP<N> WEB ADDRESS ATTRIBUTE LIST

<b>Description</b>	Defines the <i>WWW homepage</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	wwwHomePage

### 3.9.25 LDAP<N> COMPANY ATTRIBUTE LIST

<b>Description</b>	Defines the <i>company name</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	company

### 3.9.26 LDAP<N> ROOM NUMBER ATTRIBUTE LIST

<b>Description</b>	Defines the <i>room number</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	roomNumber

### 3.9.27 LDAP<N> BUSINESS STREET ATTRIBUTE LIST

<b>Description</b>	Defines the business street address attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	streetAddress

### 3.9.28 LDAP<N> BUSINESS POSTAL CODE ATTRIBUTE LIST

<b>Description</b>	Defines the <i>business postal code</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	postalCode

### 3.9.29 LDAP<N> BUSINESS CITY ATTRIBUTE LIST

<b>Description</b>	Defines the <i>business city</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	postalAddress

### 3.9.30 LDAP<N> BUSINESS STATE ATTRIBUTE LIST

<b>Description</b>	Defines the <i>business state</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	st

### 3.9.31 LDAP<N> BUSINESS COUNTRY ATTRIBUTE LIST

<b>Description</b>	Defines the <i>business country</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	co

### 3.9.32 LDAP<N> HOME STREET ATTRIBUTE LIST

<b>Description</b>	Defines the <i>home street address</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	homeStreetAddress

### 3.9.33 LDAP<N> HOME POSTAL CODE ATTRIBUTE LIST

<b>Description</b>	Defines the <i>home postal code</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	homePostalCode

### 3.9.34 LDAP<N> HOME CITY ATTRIBUTE LIST

<b>Description</b>	Defines the <i>home city</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	homePostalAddress

### 3.9.35 LDAP<N> HOME STATE ATTRIBUTE LIST

<b>Description</b>	Defines the <i>home state</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	homeState

### 3.9.36 LDAP<N> HOME COUNTRY ATTRIBUTE LIST

<b>Description</b>	Defines the <i>home country</i> attribute
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	homeCountry

## 3.10 MITEL 5000 DIRECTORIES

Configuration can contain up to 5 directories. Directory parameters are numbered with the same index number <n> for each directory; the different directories are consecutively numbered starting with 1.

For n = 1, the index number can be omitted.

### 3.10.1 A5000<N> NAME

<b>Description</b>	Directory name displayed in BluStar client
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Shared with 8000i but differing by index number.

### 3.10.2 A5000<N> SERVER

<b>Description</b>	Mitel 5000 server
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	User ID, password, host name and port combined in the expression <user ID>:<password>@<host name>:<port>
<b>Default value</b>	(none)
<b>Remark</b>	User ID and password are optional. User ID and password (if applicable) need to be encrypted (use Mitel's SeC encryption tool). The directory will be discarded if this parameter is empty.

### 3.10.3 A5000<N> MULTI-SITE

<b>Description</b>	Enable Mitel 5000 multi-site feature
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer (Boolean)
<b>Value range</b>	0 (false), 1 (true)
<b>Default value</b>	0

### 3.10.4 A5000<N> MULTI-SITE NAME

<b>Description</b>	Multi-site installation name
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.10.5 A5000<N> FIELD ID

<b>Description</b>	Field containing the dataset ID
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.10.6 A5000<N> FIELD LAST MODIFIED

<b>Description</b>	Field containing the dataset's last modification date and time
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.10.7 A5000<N> MAX TIME VARIANCE

<b>Description</b>	Time (in minutes) after which a cached entry is considered outdated
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	n/a
<b>Default value</b>	(none)

### 3.10.8 A5000<N> IMAGE SERVER URI

<b>Description</b>	URL to access pictures of users in the A5000 database
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	A valid URL
<b>Default value</b>	(none)

### 3.10.9 A5000<N> PICTURE EXTENSION

<b>Description</b>	extension of user picture files (could be jpeg, png, ...)
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	A valid image file extension (e. g. jpg, png, etc.) without “.”
<b>Default value</b>	(none)

## 3.11 LOGGING

### 3.11.1 LOG MODULE SIP

<b>Description</b>	SIP client log detail level
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0..9
<b>Default value</b>	3

### 3.11.2 LOG MODULE USER INTERFACE

<b>Description</b>	Client log detail level
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	0..10
	0 Error
	1 Warning
	2 Success
	3 Trace
	4 Extended trace 4
	5 Extended trace 5
	7 Extended trace 6
	8 Extended trace 7
	9 Extended trace 8
	10 Extended trace 9
<b>Default value</b>	3

### 3.11.3 MAX LOG FILES

<b>Description</b>	Maximum number of log files
<b>Recommended in</b>	BSCpc.cfg, BSCpc_<user>.cfg, BSCpc_<user>_local.cfg
<b>Data type</b>	Integer
<b>Value range</b>	>= 0
<b>Default value</b>	10

## 3.12 ERROR REPORTING

### 3.12.1 UPLOAD SYSTEM INFO EMAIL

<b>Description</b>	The mail address to send the error report to
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	A valid e-mail address
<b>Default value</b>	(none)
<b>Remark</b>	When using MAPI some clients require ‘SMTP:’ as prefix for mail addresses

### 3.12.2 UPLOAD SYSTEM INFO EMAIL METHOD

<b>Description</b>	Specifies the e-mail send method
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Enumeration (String)
<b>Value range</b>	None SMTP MAPI
<b>Default value</b>	(none) or “None”
<b>Remark</b>	If left empty or set to “None”, the error reporting feature will not be available. If “SMTP” is used, the <b>upload system info smtp server</b> setting must be entered as well.

### 3.12.3 UPLOAD SYSTEM INFO SMTP SERVER

<b>Description</b>	SMTP server IP address or host name
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Only required if <b>upload system info email method</b> is set to “SMTP”.

### 3.12.4 UPLOAD SYSTEM INFO SMTP SERVER PORT

<b>Description</b>	SMTP server port
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer
<b>Value range</b>	Valid IP port number (0-65535)
<b>Default value</b>	0
<b>Remark</b>	Only required if <b>upload system info email method</b> is set to “SMTP”.

### 3.12.5 UPLOAD SYSTEM INFO SMTP ENCRYPTION

<b>Description</b>	Specifies if a SSL (encrypted) connection is to be used when connecting to the SMTP server
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer (Boolean)
<b>Value range</b>	0 (false), 1 (true)
<b>Default value</b>	0
<b>Remark</b>	Only required if <b>upload system info email method</b> is set to “SMTP”.

### 3.12.6 UPLOAD SYSTEM INFO SMTP AUTH ENABLED

<b>Description</b>	Specifies if the SMTP server requires authentication. If configured, the user ID and password fields must be set.
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	Integer (Boolean)
<b>Value range</b>	0 (false), 1 (true)
<b>Default value</b>	0
<b>Remark</b>	Only required if <b>upload system info email method</b> is set to “SMTP”.

### 3.12.7 UPLOAD SYSTEM INFO SMTP AUTH NAME

<b>Description</b>	The user identity needed to authenticate with the SMTP server
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Only required if <b>upload system info email method</b> is set to “SMTP”. Needs to be encrypted (use Mitel’s SeC encryption tool).

### 3.12.8 UPLOAD SYSTEM INFO SMTP AUTH PASSWORD

<b>Description</b>	Password to authenticate with the SMTP server
<b>Recommended in</b>	astra.cfg, BSCpc.cfg
<b>Data type</b>	String
<b>Value range</b>	n/a
<b>Default value</b>	(none)
<b>Remark</b>	Only required if <b>upload system info email method</b> is set to “SMTP”. Must be encrypted (use Mitel’s SeC encryption tool).